

# User guide for MULTIPASS example

Michael Hubbard

University of Surrey

Github: thehubbard

July 21, 2020, revision 1.0

## 1 What is MULTIPASS?

MULTIPASS is an acronym for **M**Ultiple **T**ime constant **P**sd scintill**A**tion emi**SS**ion and is an example code that extends Geant4 such that scintillation emission with more than two decay time constants can be modelled. It is based on the code for simulating the EJ-276 detector system in Michael Hubbard's PhD thesis.

## 2 Code design and layout

The layout of the files follows the standard of other examples provided by Geant4. Headers are found in the `include` directory with corresponding source files located in `src`

```
[User: MULTIPASS]$ ls --group-directories-first
__DOCS__ ChangeLog.md      MULTIPASS.cc      ScanningTable.mac  STsubloop_X.mac
include  CMakeLists.txt   photon.mac        singlescint.mac    STsubloop_Y.mac
random   defaults.mac          README.txt        singlescint.rndm   subloop_xdim.mac
src      gui.mac               reviewEvent.mac   slabLoop.mac       vis.mac
```

The equivalent to the main is `MULTIPASS.cc`. There are a variety of macros that have been created, which are either for simulations or visualisations. Inside the `include` directory is the `cxxopts.hpp` header, this is an external lightweight C++ option parser library. The key files in this simulation are the `G4OpticalPhysicsMod` and `G4ScintillationMod`, which are modifications of the original scintillation and optical physics files that now allow for multiple time constants to be simulated. An overview for the rest of the files can be found in Table. 1

## 3 Compiling

The MULTIPASS source code has been build and tested again Geant4.10.04.p01 other versions may work. For details on versions of ROOT and cmake, review the source code.

Create a build directory for example `build_MULTIPASS`.

```
[User: ~]$ mkdir build_MULTIPASS
[User: ~]$ cd build_MULTIPASS
[User: build_MULTIPASS]$
```

Then inside this directory, compile using the standard cmake method.

```
[User: build_MULTIPASS]$ cmake -DGeant4_DIR=path/to/geant4/install/directory
path/to/source
```

then use `make` to produce the executable file.

| File                               | Description   |
|------------------------------------|---|
| G4OpticalPhysicsMod                | Modified Optical physics processes.   |
| G4ScintillationMod                 | Multi time constant scintillation code.   |
| MULTIPASSActionInitialization      | Action initialisations.   |
| MULTIPASSComptonHit                | Collector for gamma interactions.   |
| MULTIPASSDetectorConstruction      | Material definitions and basic setup.   |
| MULTIPASSDetectorMessenger         | Control options for the detector.   |
| MULTIPASSEventAction               | Data collected is written to file.  |
| MULTIPASSEventMessenger            | Control of data collection.   |
| MULTIPASSHistoManager              | Data collection setup.  |
| MULTIPASSMainVolume                | Building the scintillator and PMT setup.  |
| MULTIPASSOpticalHit                | Optical photon data collection.   |
| MULTIPASSPhysicsList               | Physics processes setup.  |
| MULTIPASSPMTHit                    | Counter for detected photons that reach PMT.  |
| MULTIPASSPMTSD                     | Stores data in PMThit and Opticalhit collections.   |
| MULTIPASSPrimaryGeneratorAction    | Particle generator.   |
| MULTIPASSPrimaryGeneratorMessenger | Controller for particle generator.  |
| MULTIPASSRunAction                 | Starts the run and creates the output file.   |
| MULTIPASSScintHit                  | Energy deposited in scintillator data collector.  |
| MULTIPASSScintSD                   | Sensitive detector stores energy deposited and gamma interaction processes to relevant collections.           |
| MULTIPASSStackingAction            | Scintillation and Cherenkov counters.   |
| MULTIPASSSteppingAction            | Optical photon detection code.  |
| MULTIPASSSteppingMessenger         | Stepping action controller.   |
| MULTIPASSSteppingVerbose           | Stepping verbose output leftover from LXe example.  |
| MULTIPASSTrackingAction            | From LXe example stores track information.  |
| MULTIPASSTrajectory                | Chooses when is drawn when visualisation is enabled.  |
| MULTIPASSUserEventInformation      | Event information variables.  |
| MULTIPASSUserTrackInformation      | Track information variables.  |
| ChangeLog.md                       | Change log from EJ-276 example.   |
| CMakeLists.txt                     | For compiling the code.   |
| gui.mac                            | Visualisation setup.  |
| README.txt                         | Acronym readme file.  |
| reviewEvent.mac                    | Example of how to review an event from stored information.  |
| ScanningTable.mac                  | For replicating scanning table experiment.  |
| singlescint.mac                    | Another implementation of reviewEvent.mac with different verbose output.                                      |
| singlescint.rndm                   | Random event seed file.   |
| slabLoop.mac                       | Leftover example from EJ-200 detector for increasing volume. This no longer works but shows how to use loops. |
| STsubloop_X.mac                    | Components needed for ScanningTable.mac   |
| STsubloop_Y.mac                    | Components needed for ScanningTable.mac   |
| subloop_xdim.mac                   | Components needed for slabLoop.mac  |
| vis.mac                            | Visualisation setup component.  |

Table 1: Overview of files included in the MULTIPASS example.

```
[User: build_MULTIPASS]$ make
```

If you amend the code just make should be required to compile with the latest updates. However, if new .hh, .cc, .mac files are added the cmake command will have to be run again. New files in the include and src will not need to be added to the CMakeLists.txt, any files such as macros outside these directories need to be added to the CMakeLists.txt file.

## 4 Use

MULTIPASS has multiple options for operation to see a full extent run the file with the help command.

```
[User: build_MULTIPASS]$ ./MULTIPASS --help
- a simulation software for MULTIPASS detector
Usage:
./MULTIPASS [OPTION...]

-m, --macro arg      run macro
-r, --runmode arg    Run mode [Full, Gamma, Optics] (default: Optics)
-h, --help           Print help
```

The macro flag allows a macro file to be passed such that the simulation is started in batch mode with no visualisations enabled. There are several different run modes an overview is provided in Table. 2, the default mode is Optics.

| Mode   | Description  |
|--------|--|
| Full   | Fires a gamma-ray into the scintillator. Scintillation process is enabled and optical photons are generated when interactions occur. |
| Gamma  | Fires a gamma-ray into the scintillator. Scintillation and optical photons are disabled.   |
| Optics |  |

Table 2: Different run modes available in the MULTIPASS example.

When running the program several options are accessible by messengers. Some can only be used in certain run modes. An overview of some of the important commands is found below:

```
/MULTIPASS/detector/dimensions <x> <y> <z> <unit>
Change scintillator slab dimensions.
```

```
/MULTIPASS/detector/housingThickness <thickness> <unit>
Change scintillator housing thickness.
```

```
/MULTIPASS/detector/housingThickness <radius> <unit>
Change PMT radius
```

```
/MULTIPASS/detector/reflectivity <reflectivity>
Change percentage reflectivity accepts values from 0 to 1.
```

```
/MULTIPASS/detector/MainScintYield <scintillationYield>
Change scintillation yield in Full mode. Unit is per MeV.
```

```
/MULTIPASS/gun/particle <particle>
Choose between Gamma or Neutron. In Optics mode this selects the time constants of the particle type for simulation.
```

/MULTIPASS/gun/particleEnergy <energy> <unit>

Choose energy of the particle.

/MULTIPASS/gun/scintYield <scintillationYield>

Change scintillation yield in Optics mode. The total number of photons simulated in this mode is equal to the particle energy multiplied by the scintillation yield. Unit is per MeV.

/MULTIPASS/gun/InteractionOrigin <location>

Location of optical photon generation in Optics mode. Default is Center. Available: Center<sup>1</sup>, Back, Top, Topback, Front, Topfront, Side, Sideback, Sidefront, Cornerback, Cornerfront, Edge.

/MULTIPASS/gun/offset <offset>

Offset from nearest face(s) in Optics mode.

/MULTIPASS/gun/wavelength <wavelength>

Wavelength in nm of generated optical photons in Optics mode.

/MULTIPASS/gun/ScanTableX <position>

X positional interaction location centre in Full and Gamma mode. (0,0) is bottom left where, top is defined as face with PMT.

/MULTIPASS/gun/ScanTableY <position>

Y positional interaction location centre in Full and Gamma mode. (0,0) is bottom left where, top is defined as face with PMT.

In all modes the standard /run/beamOn starts the simulation. Each run creates a data file output. For the Gamma and Full modes, the particles interact with a spot size with a 1 cm diameter on the face of the detector. The x and y position marks the centre of the spot, this was chosen to replicate the scanning table experimental setup.

## 5 Data output

Depending on run mode the data output is different. In the HistoManager the data output it currently selected as .root, editing this file allows for other data formats to be selected. The output file name starts with the run mode and includes the number of events in the run. If the optics mode is used the emission location in terms of top right etc is stored in the name. For gamma and full modes, the x-y positional information is stored in the file name.

### 5.1 Full

Energy deposited in scintillator is recorded as both a ROOT histogram and in a ntuple. The total number of optical photons detected is also stored in a histogram. Along with separate histograms for the number of reflections and pathlength of optical photons. Two 2D histograms are also filled. One has the information relating to the emission direction of the detected photons, stored in terms of the azimuthal and polar angles. An additional 2D histogram produces pseudo pulse shapes. The x-axis is time in ns, with 1 ns intervals. The y-axis corresponds to the event number in the run.

In the ntuple along with energy deposited, the total number of reflections, number of optical absorptions, number of boundary absorptions and the information regarding scintillation emission and Cherenkov photons is stored.

### 5.2 Gamma

Only energy deposited in scintillator is recorded. This is stored in a ROOT histogram and an ntuple.

---

<sup>1</sup>American English spelling used as in programming mode Michael's brain switches to this. Mainly because of the word color in the programming languages!

### 5.3 Optics

The same as full mode data output, however, energy deposited is not recorded.